

Per-user web directories

On systems with multiple users, each user can be permitted to have a web site in their home directory using the `UserDir` directive. Visitors to a URL `http://example.com/~username/` will get content out of the home directory of the user "username", out of the subdirectory specified by the `UserDir` directive.

Topics

Per-user web directories	1
Setting the file path with <code>UserDir</code>	1
Restricting what users are permitted to use this feature	2
Enabling a cgi directory for each user	2
Allowing users to alter configuration	2
URI References	2

See also

- Mapping URLs to the Filesystem¹

Per-user web directories

Related Modules	Related Directives
<code>mod_userdir</code>	<code>UserDir</code>
	<code>DirectoryMatch</code>
	<code>AllowOverride</code>

Setting the file path with `UserDir`

The `UserDir` directive specifies a directory out of which per-user content is loaded. This directive may take several different forms.

If a path is given which does not start with a leading slash, it is assumed to be a directory path relative to the home directory of the specified user. Given this configuration:

```
UserDir public_html
```

the URL `http://example.com/~rbowen/file.html` will be translated to the file path `/home/rbowen/public_html/file.html`

If a path is given starting with a slash, a directory path will be constructed using that path, plus the username specified. Given this configuration:

```
UserDir /var/html
```

the URL `http://example.com/~rbowen/file.html` will be translated to the file path `/var/html/rbowen/file.html`

If a path is provided which contains an asterisk (*), a path is used in which the asterisk is replaced with the username. Given this configuration:

```
UserDir /var/www/*/docs
```

the URL `http://example.com/~rbowen/file.html` will be translated to the file path `/var/www/rbowen/docs/file.html`

Restricting what users are permitted to use this feature

Using the syntax show in the UserDir documentation, you can restrict what users are permitted to use this functionality:

```
UserDir enabled
UserDir disabled root jro fish
```

The configuration above will enable the feature for all users except for those listed in the `disabled` statement. You can, likewise, disable the feature for all but a few users by using a configuration like the following:

```
UserDir disabled
UserDir enabled rbowen krietz
```

See [UserDir](#) documentation for additional examples.

Enabling a cgi directory for each user

In order to give each user their own cgi-bin directory, you can use a `<Directory>` directive to make a particular subdirectory of a user's home directory cgi-enabled.

```
<Directory /home/*/cgi-bin/>
Options ExecCGI
SetHandler cgi-script
</Directory>
```

Allowing users to alter configuration

If you want to allow users to modify the server configuration in their web space, they will need to use `.htaccess` files to make these changes. Ensure that you have set `AllowOverride` to a value sufficient for the directives that you want to permit the users to modify. See the [.htaccess tutorial](#)² for additional details on how this works.

URI References

[1] <http://httpd.apache.org/docs-2.1/urlmapping.html>

[2] <http://httpd.apache.org/docs-2.1/howto/htaccess.html>